


```
[root@machine root]# tar xzvf vpnserver-5070-rtm-linux-x86.tar.gz
vpnserver/
vpnserver/vpnserver.a
vpnserver/vpncmd.a
vpnserver/hamcore.se2
vpnserver/libcrypto.a
vpnserver/Makefile
vpnserver/libssl.a
vpnserver/License_ReadMeFirst.txt
vpnserver/License_ReadMeFirstUtf.txt
vpnserver/License_ReadMeFirstSjis.txt
vpnserver/.install.sh
```

????????????vpnserver??

7.3.5 ????????????

make ???

VPN Server ??????????make ?????????? vpnserver ??????????????????????

????????????vpnserver????????????????make?????????

??1?????????????

```
[root@machine vpnserver]# make
./install.sh

Do you want to read the License Agreement for this software ?
1. Yes
2. No
Please choose one of above number:
1
```

??
???????????????????????????? SSH ???

???? Ctrl+C ?????? make ?????????????????? vpnserver ?????????????????????????????????
????????????????????

??1????????????

```
EULA

Did you read and understand the License Agreement ?
(If you couldn't read above text, Please read License_ReadMe.txt
file with any text editor.)
1. Yes
2. No
Please choose one of above number:
1
```

??1??????????
???

```
Did you agree the License Agreement ?
1. Agree
2. Do Not Agree
Please choose one of above number:
1
```

????????????????????????? vpnserver ??????????????????????

```
make[1]: Entering directory `/root/vpnserver'
ranlib libssl.a
ranlib libcrypto.a
ranlib vpnserver.a
gcc vpnserver.a -pthread -lrt -lm -lz libssl.a libcrypto.a -lpthread -ldl
-lreadline -lcurses -o vpnserver
strip vpnserver
ranlib vpncmd.a
gcc vpncmd.a -pthread -lrt -lm -lz libssl.a libcrypto.a -lpthread
-ldl -lreadline -lcurses -o vpncmd
strip vpncmd
make[1]: Leaving directory `/root/vpnserver'

[root@machine vpnserver]#
```



```
#!/bin/sh
# chkconfig: 2345 99 01
# description: SoftEther VPN Server
DAEMON=/usr/local/vpnserver/vpnserver
LOCK=/var/lock/subsys/vpnserver
test -x $DAEMON || exit 0
case "$1" in
start)
$DAEMON start
touch $LOCK
;;
stop)
$DAEMON stop
rm $LOCK
;;
restart)
$DAEMON stop
sleep 3
$DAEMON start
;;
*)
echo "Usage: $0 {start|stop|restart}"
exit 1
esac
exit 0
```

???????????????????? /opt/vpnserver.sh ???cat ??????????
????????cat ??? Ctrl+D ??????????

```
[root@machine vpnserver]# cat > /opt/vpnserver.sh
#!/bin/sh
# chkconfig: 2345 99 01
# description: SoftEther VPN Server
DAEMON=/usr/local/vpnserver/vpnserver
LOCK=/var/lock/subsys/vpnserver
test -x $DAEMON || exit 0
case "$1" in
start)
$DAEMON start
touch $LOCK
;;
stop)
```


7.3.9 ??????????

???????????? VPN Server ??Linux ????????????? Linux ?????????????????????
?????????VPN Server ???

???????????????? VPN Server ?????????????????????????????

VPN Server ?????????????

VPN Server ?????????????????root ?????????????????VPN Server ?????????????

```
[root@machine vpnserver]# systemctl start vpnserver
```

VPN Server ?????????????

VPN Server ?????????????????root ?????????????????VPN Server ?????????????

```
[root@machine vpnserver]# systemctl stop vpnserver
```

VPN Server ?????????????

VPN Server ?????????????????????????????????????

- ?????????????????????????????????
- VPN Server ?????????????????vpnserver ?????????????????????
(vpnserver?vpnservercmd ??? hamcore.se2 ??????????????????????????????)
- ??? VPN Server ?????????????????????????????

vpnserver ?????????

??VPN Server ?????????????????????
???? VPN Server ?????????????????????vpnserver ?????????????????????
????vpnserver ?????????????????????[3.2.2](#) ?????? ? ?kill????????????????

7.3.10 ?????????????

Linux ? VPN Server ???
???????????????????? ?./vpnserver start????? VPN Server ?????????????????

Windows ?????????????????? vpnserver ???
?? VPN Server ???

- ?????????????(???? [3.6 ??????????](#) ??????????) ?????????????
- ????????????????????????????? vpnserver ?????????????????????????????????

????

- [??](#)
- [3.1 ????](#)
- [3.2 ??????](#)
- [3.2.2 ????????](#)
- [3.6 ??????????](#)
- [6.6 VPN Tools ????????????](#)
- [6.6.5 "Check": SoftEther VPN ????????????????????](#)